
Leverage Analysis Unit 3 Financial Management

Capital Structure Defined

- The term capital structure is used to represent the proportionate relationship between debt and equity.
- The various means of financing represent the financial structure of an enterprise. The left-hand side of the balance sheet (liabilities plus equity) represents the financial structure of a company. Traditionally, shortterm borrowings are excluded from the list of methods of financing the firm's capital expenditure.

The capital structure decision process



While making the Financing Decision...

- How should the investment project be financed?
- Does the way in which the investment projects are financed matter?
- How does financing affect the shareholders' risk, return and value?
- Does there exist an optimum financing mix in terms of the maximum value to the firm's shareholders?
- Can the optimum financing mix be determined in practice for a company?
- What factors in practice should a company consider in designing its financing policy?

Meaning of Financial Leverage

- The use of the fixed-charges sources of funds, such as debt and preference capital along with the owners' equity in the capital structure, is described as financial leverage or gearing or trading on equity.
- The financial leverage employed by a company is intended to earn more return on the fixed-charge funds than their costs. The surplus (or deficit) will increase (or decrease) the return on the owners' equity. The rate of return on the owners' equity is levered above or below the rate of return on total assets.

Measures of Financial Leverage

- Debt ratio
- Debt–equity ratio
- Interest coverage
- The first two measures of financial leverage can be expressed either in terms of book values or market values. These two measures are also known as measures of capital gearing.
- The third measure of financial leverage, commonly known as coverage ratio. The reciprocal of interest coverage is a measure of the firm's income gearing.

Financial Leverage and the Shareholders' Return

- The primary motive of a company in using financial leverage is to magnify the shareholders' return under favourable economic conditions. The role of financial leverage in magnifying the return of the shareholders' is based on the assumptions that the fixed-charges funds (such as the loan from financial institutions and banks or debentures) can be obtained at a cost lower than the firm's rate of return on net assets (RONA or ROI).
- EPS, ROE and ROI are the important figures for analysing the impact of financial leverage.

EPS and ROE Calculations

Earnings per share =
$$\frac{\text{Profit after tax}}{\text{Number of shares}}$$

$$\text{EPS} = \frac{\text{PAT}}{N} = \frac{(\text{EBIT} - \text{INT})(1 - T)}{N}$$

Return on equity =
$$\frac{\text{Profit after tax}}{\text{Value of equity}}$$
$$\text{ROE} = \frac{(\text{EBIT} - \text{INT})(1 - T)}{E}$$

 For calculating ROE either the book value or the market value equity may be used.

Effect of Leverage on ROE and EPS

Favourable ROI > i

Unfavourable ROI < i

Neutral ROI = i

Leverage Analysis

- This analysis is conducted to understand the level of risk associated with the financing decision
- It gives the magnitude of change in one variable due to change in another variable

% change in dependent variable

• Leverage = % change in Independent variable

- There are three types of leverages
- Operating Leverage
- Financial Leverage
- Combined Levwerage

Degree of Operating Leverage

- Operating leverage affects a firm's operating profit (EBIT).
- The degree of operating leverage (DOL) is defined as the percentage change in the earnings before interest and taxes relative to a given percentage change in sales.

DOL =
$$\frac{\%}{\%}$$
 Change in EBIT
% Change in Sales
DOL = $\frac{\Delta}{\Delta}$ EBIT/EBIT
 Δ Sales/Sales

 Operating leverage can be defined as the degree of change in the level of EBIT due to a change in sales Operating leverage occurs due to presence of fixed operating cost in the business. It can also be calculated by an alternate formula:.

Contribution / EBIT

The higher the fixed cost ,the higher will be the DOL and therefore higher the operating risk

Degree of Financial Leverage

 The degree of financial leverage (DFL) is defined as the percentage change in EPS due to a given percentage change in EBIT:

$$DFL = \frac{\% \text{ Change in EPS}}{\% \text{ Change in EBIT}}$$

$$DFL = \frac{\Delta EPS/EPS}{\Delta EBIT/EBIT}$$

- Financial Leverage is the change in the level of EPS due to change in EBIT
- Financial leverage occurs die to presence of Fixed financial cost (Interest) in the business
- Alternate formula for calculating DFL is EBIT/EBT

 Lets take an example of a company A whose data is taken for two periods of time

Particulars	Period 1	Period 2
Sales	100	110
Less: Variable Cost (40% of sales)	40	44
Contribution	60	66
Less: Fixed Cost	20	20
EBIT	40	46

 Using the formula for DOL, the result is 1.5 which means that for every 1 % change in sales the EBIT will change 1.5%. I.e. the magnitude of change will be more than in proportion. But, if there are no fixed cost then the DOL will be 1 which means that if the sales change by 1% the EBIT will also change by 1 %

Combining Financial and Operating Leverages

 Operating leverage affects a firm's operating profit (EBIT), while financial leverage affects profit after tax or the earnings per share.

 The degrees of operating and financial leverages is combined to see the effect of total leverage on EPS associated with a given change in sales.

Combining Financial and Operating Leverages

 The degree of combined leverage (DCL) is given by the following equation:

$$= \frac{\% \text{ Change in EBIT}}{\% \text{ Change in Sales}} \times \frac{\% \text{ Change in EPS}}{\% \text{ Change in EBIT}} = \frac{\% \text{ Change in EPS}}{\% \text{ Change in Sales}}$$

 another way of expressing the degree of combined leverage is as follows:

$$DCL = \frac{Q(s-v)}{Q(s-v)-F} \times \frac{Q(s-v)-F}{Q(s-v)-F-INT} = \frac{Q(s-v)}{Q(s-v)-F-INT}$$

Financial Leverage and the Shareholders' Risk

- The variability of EBIT and EPS distinguish between two types of risk—operating risk and financial risk.
- Operating risk can be defined as the variability of EBIT (or return on total assets). The environment—internal and external—in which a firm operates determines the variability of EBIT
 - The variability of EBIT has two components:
 - variability of sales
 - variability of expenses
- The variability of EPS caused by the use of financial leverage is called **financial risk**. Financial risk is an avoidable risk if the firm decides not to use any debt in its capital structure.

Risk-Return Trade-off

- If the firm wants higher return (EPS or ROE) for the shareholders for a given level of EBIT, it will have to employ more debt and will also be exposed to greater risk (as measured by standard deviation or coefficient of variation).
- In fact, the firm faces a trade-off between risk and return.
- Financial leverage increases the chance or probability of insolvency.